



University of Dundee

Cellular protein extraction and Western blotting using dry transfer (iBlot system)

Madsen, Ralitsa

DOI: 10.17504/protocols.io.4r4gv8w

Publication date: 2019

Licence: CC BY

Document Version Publisher's PDF, also known as Version of record

Link to publication in Discovery Research Portal

Citation for published version (APA):

Madsen, R. (2019, Jun 26). Cellular protein extraction and Western blotting using dry transfer (iBlot system): Protocol. protocols.io. https://doi.org/10.17504/protocols.io.4r4gv8w

General rights

Copyright and moral rights for the publications made accessible in Discovery Research Portal are retained by the authors and/or other copyright owners and it is a condition of accessing publications that users recognise and abide by the legal requirements associated with these rights.

• Users may download and print one copy of any publication from Discovery Research Portal for the purpose of private study or research.

- You may not further distribute the material or use if for any profit-making activity or commercial gain.
 You may freely distribute the URL identifying the publication in the public portal.

Take down policy If you believe that this document breaches copyright please contact us providing details, and we will remove access to the work immediately and investigate your claim.



JUN 26, 2019



DOI: dx.doi.org/10.17504/protocol s.io.4r4gv8w

Protocol Citation: Ralitsa R Madsen 2019. Cellular protein extraction and Western blotting using dry transfer (iBlot system). **protocols.io**

https://dx.doi.org/10.17504/p rotocols.io.4r4gv8w

MANUSCRIPT CITATION:

This protocol is an amalgamate of previous protocols provided by Dr Gemma Brierley (Institute of Metabolic Science, University of Cambridge) and Dr Tijana Mitic (CVS, University of Edinburgh), with additional modifications based on my own PhD/postdoc experience.

Cellular protein extraction and Western blotting using dry transfer (iBlot system)

Ralitsa R Madsen¹

¹University of Edinburgh



Ralitsa R Madsen University College London, University of Edinburgh, Universi...

ABSTRACT

A generic protein extraction and Western blotting protocol, allowing both for total cell lysis or cytoplasmic protein extraction only. The cytoplasmic extraction version has been used when Western blotting for PI3K and MAPK/ERK signalling components; total cell lysis with sonication has been used when Western blotting for histones.

GUIDELINES

The protocol assumes that the cells have been collected as follows prior to lysis: 1) Washed once with cold DPBS.

2) Snap-frozen on dry ice or liquid nitrogen, followed by long-term storage at

S° 08- ₿

MATERIALS

MATERIALS

COmplete™, EDTA-free Protease Inhibitor Cocktail Sigma Aldrich Catalog #05056489001
8 20X MES Buffer Thermo Fisher Scientific Catalog #NP0002
NuPAGE Antioxidant Thermo Fisher Scientific Catalog #NP0005
Molecular Biology Grade Water Fisher Scientific Catalog #10154604
BSA Sigma Aldrich Catalog #A7906
NUPAGE LDS sample buffer (4x) Thermo Fisher Scientific Catalog #NP0007
1, NUDACE MODE CDC running buffer (20x) Therma Fisher

- a 1x NUPAGE MOPS SDS running buffer (20x) Thermo Fisher
- Scientific Catalog #NP0001

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Jun 26, 2019

Last Modified: Jun 26, 2019

PROTOCOL integer ID: 25116

Keywords: protein extraction, total cell lysate, western blot, PAGE, dry transfer, iBlot

RAD Catalog #500-0112
COmplete ULTRA Tablets Mini EasyPack PhosStop Sigma Aldrich Catalog #4906845001
X Precision Plus Protein [™] Dual Color Standards BIO-RAD Catalog #1610374
NuPAGE Sample Reducing Agent (10X) Thermo Fisher Scientific Catalog #NP0009
NuPAGE 4-12%BT midi 12 2 well PAGE gels Thermo Fisher Scientific Catalog #WG1401BOX
Blot™ 2 Transfer Stacks nitrocellulose regular size Thermo Fisher Scientific Catalog #IB23001
Minimobilon Western Chemiluminescent HRP Substrate Sigma Aldrich Catalog #WBKLS0500
EZBlue [™] Gel Staining Reagent Sigma Aldrich Catalog #G1041
X Fisherbrand [™] Cell Scrapers Fisher Scientific Catalog #11587692
XCell4 SureLock [™] Midi-Cell Thermo Fisher Scientific Catalog #WR0100
TBS/T for washes; [м] 20 millimolar (mM) Trizma base, [м] 150 millimolar (mM)
NaCl, pH = 7.6 (tip: prepare a larger volume of 10X stock solution and dilute each

SAFETY WARNINGS

time; use deionised H_2O).

Some reagents are toxic if inhaled or similar and should be handled according to the accompanying materials safety sheet.

BEFORE START INSTRUCTIONS

DC[™] Protein Assav Kit **BIO-**

Prepare the required lysis buffers depending on application

The buffers can be prepared in bulk and stored at 📲 4 °C (we have previously

stored buffers A and B for 2-3 years, amd they continued to work). Always check for precipitates in the stock before preparing a working aliquot.

Take out smaller aliquots when required and supplement with the indicated inhibitors. It might be a good idea to sterile-filter the working aliquot before use. * Add fresh before use.

Type A buffer: whole-cell lysis; relatively mild (used for immunoprecipitation of

phosphoproteincs and regular WB of cytoplasmic proteins)
[м] 20 millimolar (mM) HEPES (pH = 7.4)
м 150 millimolar (mM) NaCl
мј 1.5 millimolar (mM) MgCl ₂
[M] 10 % volume Glycerol
™] 1 % volume TritonX-100
[м] 1 millimolar (mM) EGTA (dissolves at 😗 37 °C and pH 8, stirring required)
Store at <u>8' 4 °C</u> - when needed, prepare a 10 ml working aliquot and supplement
with the following immediately before use:
[M] 1 millimolar (mM) * PMSF (prepared as 100X stock dissolved in isopropanol
and store as smaller aliquots at 📲 -20 °C ; short half-life once in aqueous
solution)
[M] 2 millimolar (mM) * Na_3VO_4 (has to be dissolved in a particular way, for more
details follow this link; prepare as 100X stock solution and store as smaller aliquots
at 🖁 -20 °C)
* 1X EDTA-free protease inhibitor tablet (to 10 ml buffer)
* 1X PhosStop tablet (to 10 ml buffer)
Type B buffer: whole-cell lysis; relatively mild (used for nitrocellulose-based reverse
phase protein arrays and regular WB of cytoplasmic proteins; for original reference,
<i>see Macleod et al. 2017 doi:</i> 10.1007/978-1-4939-7201-2) [м] 50 millimolar (mM) HEPES (pH = 7.4)
IMI 150 millimolar (mM) NaCl
[M] 1.5 millimolar (mM) MgCl ₂
IMI 10 % volume Glycerol
тиз 1 % volume TritonX-100
[м] 1 millimolar (mM) EGTA (dissolves at 🖁 37 °C and pH 8, stirring required)
[м] 100 millimolar (mM) NaF
[м] 10 millimolar (mM) Na ₄ P ₂ O ₇
Adjust pH to 7.4 and store at 👔 4 °C - when needed, prepare a 10 ml working
aliquot and supplement with the following immediately before use:
[M] 2 millimolar (mM) * Na ₃ VO ₄ (has to be dissolved in a particular way, for more
details follow this link; prepare as 100X stock solution and store as smaller aliquots
at 🖁 -20 °C)
* 1X EDTA-free protease inhibitor tablet (to 10 ml buffer)

* 1X PhosStop tablet (to 10 ml buffer)

Type C buffer: whole-cell lysis; harsh for nuclear lysis (used for WB of histones) - modified RIPA buffer (higher SDS concentration used)

נאז 20 millimolar (mM) Tris-HCl (pH = 7.5)

тмј 150 millimolar (mM) NaCl
тыllimolar (mM) Na ₂ EDTA
тмј 1 millimolar (mM) EGTA (dissolves at 📲 37 °C and pH 8, stirring required)
тмі 1 Mass / % volume SDS
тмз 1 Mass / % volume Sodium deoxycholate
тмз 2.5 millimolar (mM) Na ₄ P ₂ O ₇
[M] 1 millimolar (mM) β-glycerophosphate
1 μg/ml leupeptin
Store at 👔 4 °C - when needed, prepare a 10 ml working aliquot and supplement
with the following immediately before use:
M 1 millimolar (mM) * Na ₃ VO ₄ (has to be dissolved in a particular way, for more
details follow this link; prepare as 100X stock solution and store as smaller aliquots
at 🖁 -20 °C)
* 1X EDTA-free protease inhibitor tablet (to 10 ml buffer)
* 1X PhosStop tablet (to 10 ml buffer)
Cell lysis and protein extraction
Pre-chill the benchtop microcentrifuge to § 4 °C .
Prepare cell scraper and a beaker with PBS - this will be used to rinse the cell scraper in between
processing of different samples.
Aliguet 10 ml of stock lycic buffer and discolve the required supplements that need to be added

- 2 Aliquot 10 ml of stock lysis buffer and dissolve the required supplements that need to be added fresh (see "Guidelines" for buffer details). Keep on ice.
- 3 Allow the snap-frozen cells to thaw on ice (one plate at a time, process each well for scraping and rinse the scraper in PBS in between individual samples).
- 4 A 150 µL of ice-cold lysis buffer per well and scrape the cells on ice. Add

Note

1

The volume can be reduced to 100 µl depending on expected yield. I use this volume when working with human pluripotent stem cells which give a high protein yield from a 6-well (3-5 mg/ml); this may not be the case with other cell lines and should be tested empirically.

- 5 Transfer cell lysates to pre-labelled and pre-chilled tubes.
- 6 Incubate for minimum 🚫 00:30:00 on ice.

4

- 7 Vortex each sample for 🚫 00:00:05
- 8 If performing nuclear lysis for extraction of histones: sonicate the samples on a Diagenode
 Bioruptor using 5 pulses of 3 00:00:30 ON, 00:00:30 OFF; setting =high. Following sonication, the lysates should appear clear/runny.
- 9 Centrifuge the lysate at [4 °C and 😯 12000 x g for 🚫 00:10:00
- **9.1** In the mean time, thaw previously prepared BSA standards (0 2 mg/ml).
- **10** Transfer the supernatant to new pre-chilled tubes and discard the pellets.

Note

Stopping point: the samples can be stored at **3** -20 °C at this point and processed for protein concentration measurements at a later time. Freeze-thawing should generally be limited, but up to 3 times has worked well for me in the past (alternatively, make multiple aliquots to avoid freeze-thawing of the entire volume each time).

11 Dilute the samples for protein concentration measurements (usually 1:5 but will depend on the exact samples and the expected yield). Use molecular-grade H₂O.

Note

Remember to dilute the lysis buffer the same.

It is easiest to perform these and all subsequent dilutions in PCR strip tubes.

- Prepare DC assay solution A+S according to the manufacturer's instructions (BioRad): use
 Δ 20 μL Reagent S to Δ 1 mL Reagent A (prepare a mastermix in excess of what you will need; e.g. for loading of 8 standards and 8 samples in quadruplicate = 25 * 16 * 4 * 1.2 (excess) = 1920 ~ 2 ml (2 ml Reagent A + 40 μl Reagent S).
- 13 Add <u>A 25 µL</u> of the A+S mix to each well of a 96-well plate for protein concentration measurements (e.g. Sterilin[™] Clear Microtiter[™] Plates; Thermo Scientific Sterilin 611F96 (for absorbance measurements) #11349163)
- 14 Add <u>A 5 µL</u> of each sample or standard dilution in triplicate; use multichannel pipettor if dealing with multiple samples and all diluted in PCR strip tubes.

55

5m

Example layout

Plate 1	1	2	3	4	5	6	7	8	9	10	11	12
A	S1 (0 mg/ml)	S1	S1	G7_25	G7_25	G7_25	Lysis buffer dilutio n	Lysi s buff er diluti on	Lysi s buff er diluti on			
В	S2 (0.125 mg/ml)	S2	S2	G7_26	G7_26	G7_26						
с	S3 (0.250 mg/ml)	S3	S3	G7_27	G7_27	G7_27						
D	S4 (0.5 mg/ml)	S4	S4	G7_28	G7_28	G7_28						
E	S5 (0.750 mg/ml)	S5	S5	G7_29	G7_29	G7_29						
F	S6 (1 mg/ml)	S6	S6	G7_30	G7_30	G7_30						
G	S7 (1.5 mg/ml)	S7	S7	G7_31	G7_31	G7_31						
н	S8 (2 mg/ml)	S8	S8	G7_32	G7_32	G7_32						

I prepare my BSA standards in molecular grade H_2O and aliquot into two sets of PCR strip tubes; one set is kept at 4C (working set), and the second set is stored at -20C.

15

Add \boxed{I} 200 µL of Reagent B to each well.

- 16 Wrap plate in foil and put on an orbital shaked at 300 rpm for 👏 00:15:00 .
- 17 Read 595 nm absorbance on a suitable plate reader.
- **18** Calculate sample concentration based on the standard curve and adjusted for the applied dilution; remember to subtract the lysis buffer only blank.
- **19** Calculate the amount of sample needed for loading of the required number of wells, taking into account the required mixing with 4X LDS loading buffer and 10X Reducing Agent (RA). 10 μg

15m

sample per well in 20 μ l (for midi gels) is a good starting point for most applications, but this may require adjusting on a case-by-case basis.

Samples	Protein concent ration mg/ml (equival ent to µg/µl)	V for loading of 4 gels with 5 µg per well (prepare for 20 µg in 80 µl, load 20 µl per well)	4X LDS	10X RA	LB_top_u p	Final V
G7_25	1.54901 9608	12.9	20	8	39.1	80
G7_26	1.27634 8039	15.7	20	8	36.3	80
G7_27	0.58088 2353	34.4	20	8	17.6	80
G7_28	1.21752 451	16.4	20	8	35.6	80
G7_29	1.86213 2353	10.7	20	8	41.3	80
G7_30	1.14460 7843	17.5	20	8	34.5	80
G7_31	0.38725 4902	51.6	20	8	0.4	80
G7_32	1.58578 4314	12.6	20	8	39.4	80
G7_33	1.44117 6471	13.9	20	8	38.1	80

Example table of calculations for loading of 4 wells (3+1 extra to take loss into account). LB, lysis buffer.

Note

Once the dilutions have been prepared, return the original samples to ***** -20 °C for longterm storage. It is also possible to store diluted samples in LDS/RA at ***** -20 °C, thaw and heat for loading at a later time.

- Heat samples at 70 °C for 00:10:00 (if prepared in PCR strips, use thermocycler). It is better to use a lower temperature to limit potential protein degradation while still achieving denaturation. Once completed, leave the samples to cool off at Room temperature ; pulsespin to pull-down any condensed liquid.
- 21 In the meantime, prepare running buffer according to manufacturers conditions (use 20X MOPS or 20X MES stock buffers choice will depend on the size of your proteins of interest; use

deionised H2O for dilution).

Note

For the inner gel chamber, prepare a separate aliquot of running buffer and supplement with NuPAGE Antioxidant (\pm 500 µL per \pm 200 mL).

22 Load each sample using gel loading tips; load \bot 10 µL protein ladder at the start and/or end of the gel (or as required). Run the gel at 120V until the dye front has reached the plate bottom (usual run time \bigcirc 02:00:00).

Note

For good results, it is absolutely essential to mix the samples before loading!

Note

Note that each midi tank can take 4 gels, however, loading of the gels becomes more difficult when they face backwards and may result in imprecision. It is best to stik to 12-well gels or less to minimise sample diffusion which takes place the longer the samples sit without external voltage during loading.

Transfer, blocking and primary antibody incubation

- 23 Prepare blocking buffer: [M] 3 Mass / % volume BSA to 1X TBS/T (Tween-20 at 0.1 %).
- 24 Prepare the required materials for transfer: trays with EZ gel staining reagent, trays with doubledeionised H₂O for filter paper wetting, tissue paper, scalpel, forceps, transfer packs, iBlot2 machine.
- 25 When the gel has finished running, dissassemble the casette, cut excess gel material off and transfer the gel using the iBlot2 system according to the manufacturer's instructions (Programme P3 for $\bigcirc 00:07:00$ is a good starting option, but may require changing based on protein of interest). When assembling the gel transfer stack, wet the filter paper in double-deionised H₂O and tap dry on some tissue paper before putting on top of the gel; this will reduce water-copped corrosion and the formation of "green" streaks on the membrane).
- 26 Once transferred, cut the membrane if necessary and decide on a marking system to be able to track the identify of the membrane if multiple membranes are being transferred (e.g. corner triangles cut with scalpel; number identifying gel number). Transfer the membrane to a box with blocking solution covering the entire gel. Put to rock on a shaker for 45 minutes to 1 hour.

10m

- 27 Stain the transferred gels in EZ Blue solution for 01:00:00, then destain using deionised H₂O. Both steps should be performed on a shaker. The gels can be imaged (epi-illumination or 700/800 nm fluorescence) several days later if necessary leave on bench at room temperature once destaining completed.
- **28** Prepare dilutions of primary antibody in blocking buffer according to the manufacturer's instructions.
- 29 Once the membrane has finished blocking, remove the blocking solution (can be reused), and add the primary antibody dilution so that it covers the entire blot surface. Incubate at 4 °C with rotation: typically overnight, but can be left for longer if necessary.

Secondary antibody incubation and ECL detection

- **30** Decant used primary antibody into original tube (for reuse) and return to the fride (primary antibody should be supplemented with 0.02 % sodium azide for continued fridge storage).
- **31** Wash the membrane 5X for 5 minutes each in 1X TBS/T buffer.
- **32** Dilute the required secondary antibody in blocking buffer. We typically use 1:10,000 dilutions of either one of the following antibodies: anti-rabbit IgG HRP-linked antibody (CST #7074S), anti-mouse IgG HRP-linked antibody (7076S).
- **33** Incubate the membrane in secondary antibody for 🐑 01:00:00 at 😮 Room temperature on a shaker. Make sure that the solution covers the entire surface of the membrane.
- **34** Decant secondary antibody and store in fridge for one more reuse if necessary.
- **35** Wash the membrane 5X for 5 minutes each in 1X TBS/T buffer.
- **36** Prepare ECL solution according to the manufacturer's instructions. Use 2 ml ECL mix per 10 cm x 8 cm membrane.
- **37** Place the membrane on a flat surface (e.g. glass plate), making sure that excess washing solution has been drained off, and apply the ECL solution. Ensure that the blot is covered evenly.
- **38** Incubate for 00:05:00 , then proceed with detection using a chemiluminescence imaging system.

Note

Tip: make sure the imaging settings are written down in a readme.txt file, alongside experimental information (samples, transfer condition, antibody dilutions and lot numbers, blocking conditions)

39 Once detected, the membrane can be stored in TBS/T in the fridge for up to two weeks if required for repeated incubations.